SCRIPTLOGIC CORPORATION

BridgeTrak® 8.0

BridgeAccess User's Manual

The *Next* Generation of BridgeTrak©

© 2008 ScriptLogic Corporation All rights reserved.

BridgeAccess and *BridgeTrak* are trademarks of ScriptLogic Corporation. *BridgeAccess* User's Manual and *BridgeAccess* software is furnished under license and may only be used or copied in accordance with the terms of such license.

This user's guide and *BridgeAccess* are proprietary to ScriptLogic Corporation and contain certain confidential information and trade secrets of ScriptLogic Corporation which are protected by United States and International laws and treaties. The content of this user's guide is furnished for informational use only, is subject to change without notice, and should not be construed as a commitment by ScriptLogic Corporation. ScriptLogic Corporation assumes no responsibility or liability for any errors or inaccuracies that may appear in this manual.

Unauthorized duplication or distribution of this material is strictly prohibited. All data, reports, and information are the sole property of ScriptLogic Corporation. Except as permitted by such license, no part of this publication may be reproduced, stored in a retrieval system, or transmitted, in any form or by any means, electronic, recording, or otherwise without the prior written permission of ScriptLogic Corporation.

All other trademarks are the properties of their respective owners.

Contents

1 Overview 4
2 Logging into BridgeAccess 5
2.1 Logging in as a Customer 5
2.1.1 Customer Registration and Validation 6
2.1.1.1 Validating Customers to use BridgeAccess 7
2.1.1.2 Customer Registration 8
2.2 Logging in as an Administrator 12
3 Customizing BridgeAccess for your Organization and your Customers 14
3.1 System Options 14
3.1.1 Email Configuration 16
3.1.2 General Tab 18
3.1.3 Logo Settings Tab 21
3.1.4 Issue Activity Settings Tab 24
3.1.5 Report Settings Tab 27
4 Defining Layouts 31
4.1 Defining a New Layout 32
4.1.1 Adding Fields to a Layout 33
4.1.2 Sequencing Fields 34
4.1.3 Assigning BridgeAccess Layouts to Companies 35
5 Viewing Issues 36
5.1 The View Issue Window 38
5.1.1 Editing Issues 39
5.1.2 Submitting Issues 41
6 The Knowledge Base 44

1 Overview

BridgeAccess is a self-help solution for your Customers. It provides them with an online interface to your help desk offering user-friendly navigation and easy access to their Issues and your organization's *BridgeTrak* Knowledge Base.

Through a standard internet connection and browser, an unlimited number of your Customers can:

- Enter new Issues
- Monitor the Status of their Issues
- Perform Queries on their Issues
- Access your *BridgeTrak* Knowledge Base

By affording your Customers these capabilities, your organization can:

- Control costs by reducing the number of phone calls your technicians must answer.
- Reduce the number of new Issues by providing self-help via access to your *BridgeTrak* Knowledge Base.
- Reduce the number of "Status" phone calls by enabling your Customers to check on the Status of their Issues without calling your help desk.

2 Logging into BridgeAccess

You can log into *BridgeAccess* in one of two capacities: Administrator or Customer. When you log in as an Administrator, you have the ability to establish the parameters by which your Customers can submit and review their Issues. When your Customers log in, they will be permitted to/limited from accessing the functions you (as an Administrator) have defined, such as the ability to access the Knowledge Base or view the Message Board.

2.1 Logging in as a Customer

When you initially open *BridgeAccess* in your web browser, the Customer Login window is displayed:

Enter your name and password in the appropriate fields (as defined on the BridgeAccess tab of the Customer window in *BridgeTrak*) and then click on **Submit**.

NOTE
The Register and Forgot Logon Name and/or Password links displayed in the Customer Login window may be hidden from view. See Section 4.1.2 of this guide for instructions on disabling one or both of these links.

If you are a new *BridgeAccess* user, click on the **Register** link. *BridgeAccess* will display the Registration window, shown below:



(For more information, see "Customer Registration and Validation" in this user's manual.)

If you forget your password, click on the **Forgot Logon Name and/or Password** link. *BridgeAccess* will display the Forgot Logon Name and/or Password window, shown below:


Forgot Logon Name and/or Password
If you have forgotten your logon name and/or password, enter your email address below.
Your information will be emailed to you.
Email Address
Submit
Close

Enter your email address, and depending upon the settings in System Options, *BridgeAccess* will send an automatic response. (For more information, see "Forgot Password Page Configuration Tab" in this user's manual.)

NOTE
If your email settings have not been configured in the System Options window by your System Administrator, the "Register" and "Forgot Logon Name and/or Password" ***links will not be visible***. Email configuration is essential to the basic functionality of BridgeAccess and should be set up as a first step by the System Administrator.

2.1.1 Customer Registration and Validation

Before your Customers can log in to *BridgeAccess* to review and submit Issues, they must first be validated. This can be accomplished in one of two ways:

- Your Customers can register online. Their registration requests will be sent to *BridgeTrak* where they will be held in a "validation queue" where they can be "Approved" or "Denied" by the *BridgeAccess* Administrator.

- You can validate them, without registration, via Customer Setup in *BridgeTrak.*

These procedures are detailed in the sections that follow.

2.1.1.1 Validating Customers to use BridgeAccess

As mentioned earlier, Customer validation for *BridgeAccess* is done in *BridgeTrak*. To validate your Customers to use *BridgeAccess*, in *BridgeTrak*, click on **Setup | Customers**. Select the Customer that you want to validate and open the Customer – Edit window, shown below:



Click on the *BridgeAccess* tab and *BridgeTrak* will display the window, shown below:



Complete the information on the *BridgeAccess* tab, using the table below as a guideline.

Field	Description
Grant Customer BridgeAccess Login Privilege	Check this box to allow the Customer to login to *BridgeAccess*. Checking this box will enable all other fields in this window.
Login Name	Enter the name you want the Customer to use when logging into *BridgeAccess*.

Field	Description
Cannot Change Password	Check this box if you want to manage the Customer's password. If you check this box, the Customer's **Change Password** option in the **Tools** menu will be disabled.
Must Change Password	Check this box if you want to force the Customer to change his/her password.
View Company Issues	Check this box if you want to allow the Customer to view all Issues reported by his/her Company.
View Department Issues	Check this box if you want to limit the Issues that the Customer can view to only those reported by his/her Department.
View Location Issues	Check this box if you want to limit the Issues that the Customer can view to only those reported by his/her Location.
Last Login	The **Last Login** field is display-only and shows the last date and time that the Customer logged into *BridgeAccess*.

2.1.1.2 Customer Registration

Registration is done via *BridgeAccess* by the Customer. If a Customer has been validated in *BridgeTrak*, there is no need for him/her to register via *BridgeAccess*. However, if the Customer is not validated, when the login window is displayed, he/she can click on the **Register** link. *BridgeAccess* will display the Registration window, shown below:



After completing the information, the Customer will click on **Submit** and the data will be sent to *BridgeTrak*. *BridgeTrak* will look at the email address and compare it to those already in the database.

If the email address is already in the *BridgeTrak* database, the following message will be displayed:



If the Customer's email address is not in the *BridgeTrak* database, *BridgeAccess* will display the message shown below:

Your registration to BridgeAccess has been evaluated and approved.
You will be able to coninue to submit any isses using BridgeAccess
Click here to continue login to BridgeAccess.

When the Customer receives this message, his/her information is sent to *BridgeTrak* where the Administrator can Approve or Deny the Customer's access to *BridgeAccess*.

Customer registration information is held in a queue in *BridgeTrak*. From this queue, the BridgeAccess Administrator can choose to:

- Approve validation for the Customer and retain all the Issues that he/she has submitted.
- Deny validation for the Customer and delete any Issues that he/she has submitted.
- Deny validation for the Customer and retain any Issues that he/she has submitted.

This queue can be accessed by clicking on **Modules | BridgeAccess | BridgeAccess – Customer Validation**. *BridgeTrak* will display the Registered Customers window, shown below:



From this window you can edit each registration entry and approve or deny access to the *BridgeAccess* system. To edit a registration entry, click on it and then click on **Edit**. *BridgeTrak* will display the Customer Validation window, shown below:



The information that the Customer entered in the Registration window will appear in the Customer Validation window.

Next to the Company Name field is a browse button ( ). When you click on **Browse**, *BridgeTrak* will display the Companies window, shown below, where you can search for the Company for which the Customer works.



To the right of the Browse button is a Match/No Match indicator. If the Company name that the Customer entered is in the database, the indicator will display Match ( ). If the Company name is not in the database, the indicator will display No Match ( ).

In addition, the Customer Validation window contains the following checkboxes:

Checkbox	Description
View Company Issues	Check this box to allow the Customer to view all Issues reported by his/her Company.
View Department Issues	Check this box to allow the Customer to view only those Issues reported by his/her Department.
View Location Issues	Check this box to allow the Customer to view only those Issues reported by his/her Location.
Open Customer Setup Window After Validation	Check this box to have *BridgeTrak* automatically open the Customer – Edit window immediately after validating the Customer so that you can enter all pertinent Customer information.

The function buttons at the bottom of the Customer Validation window allow you to do the following:

Click On	To
Approve	Approve and validate the Customer's registration and accept any Issues that he/she has submitted. If the Company for which the Customer works is not in the database, *BridgeTrak* will display the message, shown below:  Click on **Yes** to create a new Company record. Initially, the new Company record will contain only the **Company Name**. You can edit the record via **Setup | Companies** to include additional Company information. Click on **No** to create the Customer record without a Company. Click on **Cancel** to cancel the validation process and return to the Customer Validation window.
Deny (Delete)	Decline the Customer's registration and delete any Issues that he/she has submitted.

Click On	To
Deny (Retain)	Decline the Customer's registration and prohibit further access to *BridgeAccess*. If the Customer has submitted Issues, *BridgeAccess* will display the message, shown below:  Click on **Yes** to retain the Issues submitted by the Customer. Click on **No** to delete the Issues submitted by the Customer. Click on **Cancel** to cancel the Operation and return to the Customer Validation window.
Cancel	Cancel the validation process and return to the Registered Customer window.

2.2 Logging in as an Administrator

When you open *BridgeAccess* in your web browser, the Customer Logon window is displayed:

To login as an Administrator, click on the **Click here if you are a BridgeTrak Administrator** link. *BridgeAccess* will display the Administrator login window, shown below:

In the **Logon Name** and **Password** fields, enter your logon name and password as defined in the User Setup window in *BridgeTrak*, shown below:



If you are not defined as a *BridgeTrak* User, you will be unable to log into *BridgeAccess* as an Administrator.

3 Customizing BridgeAccess for your Organization and your Customers

BridgeAccess gives you the ability to tailor the software to best meet your needs as well as the needs of your Customers. You can define screen layouts on a per Company basis and each layout can be configured to allow your Customers to view and enter the information that you specify.

3.1 System Options

The settings defined in the System Options window will apply to all of your Customers who use *BridgeAccess*. System Options enables you to do the following:

- Set up contact information for your Customers including your email link, company address and phone number, and your website address.
- Select whether or not you want your Customers to view the *BridgeTrak* Message Board.
- Select whether or not you want your Customers to view the *BridgeTrak* Knowledge Base.
- Set up auto-responses for those Customers who forget their passwords.
- Select whether or not you want Customers to register themselves from the Customer login window.
- Include your Company's logo in the screen header and sign on screens.
- Choose the Activity Types and Activity fields that you want to make available to your Customers.

To access the System Options window, click on **Tools | Setup | System Options**. *BridgeAccess* will display the System Options window, shown below:



The System Options window is comprised of five tabs. They are:

- Email Configuration
- General
- Logo Settings
- Issue Activity Settings
- Report Settings

Each of these tabs is described in detail in the sections that follow.

3.1.1 Email Configuration

When the System Options window is opened, the Email Configuration tab, shown below, is displayed:



Email is a critical component of BridgeAccess. When a Customer registers for self-help through BridgeAccess, they receive an email to notify them of their successful registration and ultimately, approval. If they forget their password, they are notified via email of their new (reset) password. Knowledge Base articles can be forwarded by email, which facilitates greater communication between Customers. For all of these reasons, it is essential to properly configure your email parameters on the Email Configuration tab of the System Options window.

On this tab, you will configure the following fields:

Field	Description
From Name	Enter the name that you want to display in the "From" line of your email message.
From Email Address	Enter the address from where the email message is being sent.
SMTP Server	Enter your SMTP server name.
Authentication Checkbox	Check the "My Server Requires Authentication" checkbox if your SMTP server

Field	Description
	requires authentication before sending mail.
SMTP User Name	Enter the user name for the account that will be sending mail on the SMTP server.
Password	The **Password** field is display-only. It is populated by clicking on the **Change** link to the right of the field and then assigning and confirming a new Password.
Forgot Password Subject	When a Customer requests his forgotten password, this is the subject of the email he or she will receive notifying them of their new password.
Forgot Password Message	You can optionally specify a message for the user to receive in the email containing their new password. BridgeAccess will automatically generate a brief message giving them the new password.
Customer Registration Subject	When a Customer first registers for access to BridgeAccess, this is the subject of the email they will receive to confirm their registration.
Customer Registration Message	When the Customer first registers, you can specify a brief message that they will receive in their registration email.
Customer Approval Subject	When you approve a Customer's registration, they will receive an email notifying them that the registration was approved. This field specifies the subject for that email.
Customer Approval Message	When you approve a Customer's registration, you can optionally specify a brief message to appear in the body of their approval email.
Signature Block	When one of the above emails are generated by BridgeAccess, this will be the signature block that will appear after the **Message Body**.

3.1.2 General Tab



The General tab contains basic information about your BridgeAccess configuration.

In the **Email Link** field, enter the email address you want your Customers to use when contacting your help desk.

In the **Company Information** text field, enter any contact information that you want your Customers to see. In the **Company Website** field, enter your organization's website address.

Check the **Display Message Board** box if you want to include the Message Board (created in *BridgeTrak*). The Message Board headlines will be displayed across the top of your Customers' screens and they will be able to view the Message Board, when they click on the **Read the Message** link.

Check the **Display Knowledge Base** box if you want the Knowledge Base to be available for your Customers to see. The Knowledge Base will be accessed from the BridgeAccess Tools menu item.

Check the **Display Register Link** box if you want your Customers to have the option to create their own login id and password from the main login page of BridgeAccess.

Check the **Display Forgot Logon Name and/or Password Link** box if you want Customers to request their login information be emailed to them from the help desk.

The information entered on the General tab will be presented to your Customers as detailed in the sections that follow.

Your contact information will be displayed when your Customers click on **Help | Contact Us**. *BridgeAccess* will display the Contact Us window, shown below:



When your Customers click on **Help | Company Website**, they will be linked to the website address specified in the **Company Website** field.

If you checked the **Display Message Board** box, the message board headline created in *BridgeTrak*, will be displayed as shown in the example below:

In order for the Headline and Message to be displayed in BridgeAccess, you must specify to do so in the Manage Message Board window in BridgeTrak for Windows or Web. This window is shown below:



In the Manage Message Board window, click on the Message that you want to display in *BridgeAccess*, and then click on **Edit**. *BridgeTrak* will display the Message – Edit window, shown below:



From the View Option drop-down menu, choose one of the following:

Choose	To
BridgeTrak	Display the Headline and Message in *BridgeTrak* only.
BridgeAccess	Display the Headline and Message in *BridgeAccess* only.
Both	Display the Headline and Message in both *BridgeTrak* and *BridgeAccess*.

For any Headlines that you have selected to display in BridgeAccess, when your Customers position their cursor over the Headline, the **Read the Message** link will be displayed. Clicking on this link will display the full message board, as shown in the example below:


Message - Microsoft Internet Explorer
Kemma Software Introduces BridgeTrak 7.0
Kemma Software Introduces BridgeTrak 7.0.
BridgeTrak keeps your Support Center running smoothly and efficiently by automating all aspects of Issue Management. BridgeTrak offers maximum flexibility, accessibility, scalability required for today's fast paced support operations.

If you checked the **Display Knowledge Base** box, all Knowledge Base Articles that were not reserved for Internal Use Only in the BridgeTrak help desk will be available from the list of menu items.

The Login screen for BridgeAccess will display the **Register** link and the **Forgot Logon Name and/or Password** link if these boxes have been checked.



3.1.3 Logo Settings Tab

The Logo Settings tab in the System Options window is where you can personalize your *BridgeAccess* windows by displaying your organization's name and logo. To change the name and logo, click on the Logo Settings tab in the System Options window. *BridgeAccess* will display a window like the one shown below:

The **Header Logo** pane is where you choose the Header that will appear on the top of each *BridgeAccess* window. The size of the graphic for the Header Logo should be: Width - 625, Height - 67. The **Logon Screen Logo** pane is where you choose the logo that will appear on the *BridgeAccess* logon screen. The size for the graphic for the Logon Screen Logo should be: Width - 100, Height - 90.

NOTE
Any type of graphics file that is supported by Web Browsers can be used for the Header Logo and Logon Screen Logo. We recommend the .gif and .jpg file types. These are the most common and provide the best resolution when viewed using a browser.

To select a file, click on **Browse**. *BridgeAccess* will display a standard Windows directory, like the one shown below:


Open
Look in:
My Documents
Tools
My Recent Documents
Desktop
My Documents
My Computer
My Network Places
Name
Size
Type
Date Modified
elbr.gif 13 KB GIF Image 10/28/2005 9:
emaildetails.gif 12 KB GIF Image 10/14/2005 7:
emailhistory.jpg 123 KB Paint Shop Photo Al... 10/18/2005 1C
emailhistorytab.gif 19 KB GIF Image 10/13/2005 11
emaillog.gif 13 KB GIF Image 10/13/2005 1:
emaillogbr.gif 13 KB GIF Image 10/28/2005 9:
emailqueue.jpg 99 KB Paint Shop Photo Al... 10/18/2005 1C
emailqueueicon.gif 2 KB GIF Image 10/14/2005 6:
emailqueuewindow.gif 16 KB GIF Image 10/14/2005 6:
emailsettings.gif 15 KB GIF Image 10/25/2005 12
emailsettings.jpg 37 KB Paint Shop Photo Al... 9/6/2005 10:1
emailsettingswindow.gif 15 KB GIF Image 10/25/2005 12
emailsetup.doc 95 KB Microsoft Word Doc... 9/6/2005 8:31
emailsetup.jpg 75 KB Paint Shop Photo Al... 9/6/2005 8:29
File name:
Files of type:
All Files (*.*)
Open
Cancel

Click on the file that you want to use for the logo and then click on **Open**. The path and file name will appear in the **Browse** box on the Logo Settings tab. Click on **Select** and then click on **Apply**.

Your organization's name and logo will now appear on the *BridgeAccess* windows. The example below shows the sample Company's (X-Track Corporation) name and logo.



3.1.4 Issue Activity Settings Tab

You may not want your Customers to be able to view all Activity Types that you have defined in *BridgeTrak*. The Issue Activity Settings tab enables you to select the Activity Types and Activity Fields that you want to permit your Customers to view.

When you click on the Issue Activity Settings tab, *BridgeAccess* will display the window, shown below:

The top portion of the window allows you to choose the Activity Types that your Customers will be allowed to view:



Move the Issue Activity Types that you want to permit your Customers to view from the left pane to the right pane. Use the left (<) and right (>) arrow keys to move the Activity Types back and forth between panes.

The bottom portion of the window allows you to choose the Issue Activity fields that will be displayed for your Customers as well as the order in which they will appear:



In the example below, the *BridgeAccess* Administrator has permitted Customers to view the following Issue Activity Types:

- Enhancement Request
- Install Hardware Part
- Meeting – With Customer
- Site Visit
- Telephone Support



The Administrator has also permitted Customers to view the following Activity fields:

- Date/Time
- Activity Types
- Time Spent
- Activity Billable



When the Customer logs into *BridgeAccess* to view Issues, the window below shows an example of what he/she will see:



3.1.5 Report Settings Tab

When a Customer is viewing Issues, he/she has the option of printing the Issues in report format. This is enabled when the Customer clicks on **Print Selected Issues** or **Print All Issues** in the View Issues window, as shown in the example below:


Issue No
Company
Department
Customer
Received On
Assigned User
Category
Priority
8 Titan Software, Inc. Research & Development Adam Cox January 17, 2005 X-Track Sales Low Averatec No
11 Titan Software, Inc. Research & Development Adam Cox January 17, 2005 aschmitt X-Track Sales Medium Brother Fax
23 Titan Software, Inc. Research & Development Adam Cox January 17, 2005 asharpe X-Track QA High Canon Print
47 Titan Software, Inc. Research & Development Adam Cox June 02, 2005 X-Track Budget High Canon Print
88 Titan Software, Inc. Research & Development Adam Cox August 23, 2005
89 Titan Software, Inc. Research & Development Adam Cox August 24, 2005
90 Titan Software, Inc. Research & Development Adam Cox August 24, 2005 1
91 Titan Software, Inc. Research & Development Adam Cox August 24, 2005
92 Titan Software, Inc. Research & Development Adam Cox August 24, 2005
94 Titan Software, Inc. Research & Development Adam Cox August 24, 2005
Page 1 of 3.
Check All
Uncheck All
View
Print Selected Issues
Print All Issues

The settings for the report are determined by the *BridgeAccess* Administrator. On the Report Settings tab, you can select the Report Type, Viewer Type, and any graphic files you would like to include in the header of the report (e.g., your organization's logo). When you click on the Report Settings tab, *BridgeAccess* will display the window shown below:



In the **Viewer Type** drop-down menu, select which viewer you want your Customers to see when viewing their reports. You may choose either ActiveX Viewer or Html Viewer.

ActiveX Viewer is the report viewer used with Active Reports. If you select this Report Type, when your Customers run the Issue report, they will be prompted to install the ActiveX Viewer.


Internet Explorer - Security Warning
Do you want to install this software?
Name: ActiveReports 2.0 Viewer ActiveX
Publisher: Data Dynamics, Ltd.
More options
Install
Don't Install
While files from the Internet can be useful, this file type can potentially harm your computer. Only install software from publishers you trust. What's the risk?

When the ActiveX Viewer is installed the Issues Report will be displayed as shown in the example below:



Notice the toolbar at the top of the viewer. By using the ActiveX Viewer, your Customers are offered more viewing options than those available with the Html Viewer. An example of the Html Viewer is shown below:


Export
Go To: 1 of 1 Find:
X-TRACK CORPORATION
11/14/2005 2:23:30 PM
Issues Report
Issue No : 90
Received On : August 24, 2005
Status : CLOSED
Activities on Issue Number 90
Date/Time : 8/24/2005 8:55:17 AM
Activity Type : 100 Dollar Per Hour Activity
Cost : 2800
Activity Note :
Time Spent : 1:3:34
Activity Billable : No
Entered By :
Date/Time : 11/8/2005 7:55:10 AM
Activity Type : Issue Closed
Cost : 0
Activity Note : Issue Closed by Customer acox (Adam Cox)
Time Spent : 000:00:00
Activity Billable : No
Entered By :
Activity Total Time : 1:3:34

In the **Report Logo** pane, you can personalize your *BridgeAccess* reports by including your organization's name and logo at the top of the report. The size of the graphic file should be: Width – 426, Height – 67. To select a graphics file, click on **Browse**. *BridgeAccess* will display a standard Windows directory, like the one shown below:



NOTE
Any type of graphics file that is supported by Web Browsers can be used for the Report Logo. We recommend the .gif and .jpg file types. These are the most common and provide the best resolution when viewed using a browser.

Click on the graphics file that you want to use for the logo and then click on **Open**. The path and file name will appear in the **Browse** box. Click on **Select** and then click on **Apply**. Your organization's name and/or logo will now appear on the *BridgeAccess* reports. The example below shows the sample company's (X-Track Corporation) name and logo.



4 Defining Layouts

Because you may not want all of your Customers to be able to view the same Issue information, *BridgeAccess* enables you to define layouts on a per Company basis.

When you initially log in to *BridgeAccess*, the Define Layouts window will be displayed. This window can also be accessed by clicking on **Tools | Setup | Define Layout**.



The Define Layouts window shows all *BridgeAccess* Layouts that have been defined for your organization.

The first selection in the list is "Standard Layout" which is the *BridgeAccess* default Layout. This layout is installed with your *BridgeAccess* software and it cannot be edited or deleted.

If you want to select a different layout as the default, click on it in the list and then click on **Set As Default**. The current default layout name is always displayed at the bottom of the Define Layouts window, as shown in the example below:



4.1 Defining a New Layout

To define a new Layout, click on **Add** in the Define Layouts window. *BridgeAccess* will display the Customize Layout window shown below:



The Customize Layout window initially shows the definition for the *BridgeAccess* default, "Standard Layout". In the **Layout Name** field, enter a unique name for the Layout. This field is required. The grid in the window displays seven columns, described below:

Column	Description
Delete	The **Delete** column contains a checkbox. Check each box for the fields that you *do not* want to appear in the Layout. If the checkbox is disabled (i.e., grayed-out), you are not permitted to delete it. To remove the fields from the grid, and thus from the Layout, click on **Remove**. All fields with a check in the **Delete** column will be removed.
Field Name	This is the name of the Issue field.
Default Value	If you want the Issue field to automatically populate with a specified value, indicate that value here. If a default value is not permitted, you will be unable to position your cursor in the field. Otherwise, you can select a value from a drop-down menu, or type in the text that you want to use as the default.
Required	If you want to make a field entry required, place a checkmark in the **Required** column. At Issue entry time, if your Customer does not make an entry in a required field he/she will be unable to save the Issue.
Read Only	If you want to make an Issue field read-only, place a check in the **Read Only** column. When a field is designated as read-only, your Customers will be able to view it when looking at their Issues, but at Issue entry time, the field will be disabled.
Searchable	If you want your Customers to be able to use the field when specifying search criteria, place a check in the **Searchable** column.
Printable	If you want your Customers to be able to print the field on his/her Issue reports, place a check in the **Printable** column.

4.1.1 Adding Fields to a Layout

If you want to give your Customers access to additional Issue fields, click on **Add Fields**. *BridgeAccess* will display the Add Fields window, shown below:



The Add Fields window is divided into two tabs: **Regular Fields** and **Custom Fields**. The **Regular Fields** tab lists all *BridgeTrak* Issue fields to which you can give your Customers access. The **Custom Fields** tab show the custom Issue fields defined by your organization in *BridgeTrak* (for more information, see "Custom Fields" in the *BridgeTrak User's Manual*).

Place a check next to each field that you want to add to the Layout, on both the **Regular Fields** and **Custom Fields** tabs and then click on **Save**. *BridgeAccess* will add the new fields to the grid in the Customize Layout window. Complete the selections in the grid columns for the new fields.

4.1.2 Sequencing Fields

After selecting all of the Issue fields that you want to include in your Layout, you can sequence them in any order that you like. The order that you select will be used horizontally from left to right when your Customers view Issues, and vertically when you Customers submit Issues, as shown in the examples below:

Viewing Issues Example



	Issue No	Company	Department	Customer	Received On	Assigned User	Category	Priority	
☐	8	Titan Software, Inc.	Research & Development	Adam Cox	January 17, 2005		X-Track Sales	Low	Averatec I
☐	11	Titan Software, Inc.	Research & Development	Adam Cox	January 17, 2005	aschmitt	X-Track Sales	Medium	Brother Fa
☐	23	Titan Software, Inc.	Research & Development	Adam Cox	January 17, 2005	asharpe	X-Track QA	High	Canon Pri
☐	47	Titan Software, Inc.	Research & Development	Adam Cox	June 02, 2005		X-Track Budget	High	Canon Pri
☐	67	Titan Software, Inc.	Purchasing	Terry Carrick	June 17, 2005		X-Track Sales	High	
☐	69	Titan Software, Inc.	Quality Assurance	Walter Cobb	June 23, 2005		X-Track Budget	Medium	

Submitting Issues Example



If you want to change the sequence of the Issue fields, click on **Change Sequence** in the Customize Layout window. *BridgeAccess* will display the Change Sequence window, shown below:



This window lists all fields that have been selected for the Layout. To change the position of a field within the list, click on the field and then use the up ( ) and down ( ) arrows to move the field to the correct position.

When you are satisfied with the fields' positions, click on **Save**. *BridgeAccess* will re-sequence the fields in the grid in the Customize Layout window to reflect your changes.

4.1.3 Assigning BridgeAccess Layouts to Companies

When your *BridgeAccess* Layouts have been defined in *BridgeAccess*, they will be available for selection in *BridgeTrak*. This selection can be made on a per Company basis. To select a Layout for a Company, in *BridgeTrak* click on **Setup | Companies**. Select the Company to which you want to assign a Layout and then in the Company – Edit window, click on the **BridgeAccess Layout** drop-down menu.



This menu will contain all Layouts that you have defined in *BridgeAccess* along with the Standard Layout that comes with the *BridgeAccess* installation. From the **BridgeAccess Layout** drop-down menu select the Layout that you want to assign to the Company. After saving, each time a Customer from this Company logs into *BridgeAccess*, they will be presented with this Layout.

NOTE
If a Customer is validated as a *BridgeAccess* user, but is not affiliated with a Company, the Layout that is defined as the default will be used. If no default is defined, the "Standard" *BridgeAccess* Layout will be used.

5 Viewing Issues

After logging in as a Customer, *BridgeAccess* will display the View Issues window, shown below:



The search criteria fields in this window are described below:

Field	Description
View	From the drop-down menu, the Customer can select to view his/her Issues or all Issues reported by his/her Company (depending on the options that the *BridgeAccess* Administrator has selected for the Customer). This option is determined by the settings on the **BridgeAccess** tab in the Customer window in *BridgeTrak*. (For more information, see "Validating Customers to use *BridgeAccess*" in this user's manual.)
Timeline	From the **Timeline** drop-down menu, the Customer can select the age of the Issues that he/she wants to view.
Status	From the **Status** drop-down menu, the Customer can choose which of the four *BridgeTrak* Issue Statuses he/she wants to view (Open, Closed, Suspended, or Pending, or he/she can choose to view all Issues.)
Issue No	The Customer can enter a specific Issue Number and then click on **View** to see one Issue in particular. The Customer can also click the "Submit New Issue" link in this section to submit a new Issue.

Field	Description
More Search Criteria	When the Customer clicks on the **Browse** button (...), *BridgeAccess* will display the More Search Criteria window, shown below:  From any or all three of the drop-down menus, the Customer can select additional fields to use as search criteria. The Customer may choose from Assigned User, Category, Priority, Asset, Summary, and Status. After a selection is made, *BridgeAccess* will display another drop-down menu to the right, where the Customer can choose a value.

When all selections have been made in the More Search Criteria window, click on **Done**. Then, in the View Issues table, click on **Search**. *BridgeAccess* will display all Issues satisfying the specified criteria. The Issues will be displayed in the format specified in the Customize Layout window. (For more information, see "Defining a New Layout" in this user's manual.) An example is shown below:



5.1 The View Issue Window

As discussed above, after your Customers enter their search criteria and then click on **Search**, *BridgeAccess* will display the results in a View Issues window, like the one shown below:


X-TRACK CORPORATION
New Activity Types have been added. BridgeTrak Users please review them at your earliest convenience.
Issues
Tools
Help
Logout
Welcome, Adam Cox. Today is Tuesday Nov 08, 2005
View Issues
View
Titan Software, Inc. Issues
Timeline
All Issues
Status
All Issues
Issue No
View
More Search Criteria
Search
Reset
Issue No | Company | Department | Customer | Received On | Assigned User | Category | Priority
8 | Titan Software, Inc. | Research & Development | Adam Cox | January 17, 2005 | | X-Track Sales | Low | Averatec
11 | Titan Software, Inc. | Research & Development | Adam Cox | January 17, 2005 | aschmitt | X-Track Sales | Medium | Brother F.
23 | Titan Software, Inc. | Research & Development | Adam Cox | January 17, 2005 | asharpe | X-Track QA | High | Canon Pr
47 | Titan Software, Inc. | Research & Development | Adam Cox | June 02, 2005 | | X-Track Budget | High | Canon Pr
67 | Titan Software, Inc. | Purchasing | Terry Carrick | June 17, 2005 | | X-Track Sales | High
69 | Titan Software, Inc. | Quality Assurance | Walter Cobb | June 23, 2005 | | X-Track Budget | Medium
88 | Titan Software, Inc. | Research & Development | Adam Cox | August 23, 2005
89 | Titan Software, Inc. | Research & Development | Adam Cox | August 24, 2005
90 | Titan Software, Inc. | Research & Development | Adam Cox | August 24, 2005 | 1
91 | Titan Software, Inc. | Research & Development | Adam Cox | August 24, 2005
Page 1 of 3.
Check All
Uncheck All
View
Print Selected Issues
Print All Issues

From this point, your Customers can edit, view, and print their Issues.

5.1.1 Editing Issues

To edit an Issue, select it in the View Issue window by checking the box in the left-most column of the grid. After the Issue has been selected, click on the **View** button at the bottom of the window. *BridgeAccess* will display the View/Modify Issue window, shown below:



All fields that have been defined in the Layout are displayed. The fields that the Customer is not permitted to edit are disabled.

The Activities tab shows the Activities that are associated with the Issue. Only the Activities with the Type(s) specified in the Layout are displayed.



On the Activities tab, if you want to add a note, click on **Add Note**. *BridgeAccess* will display the Add Note window, shown below:



After typing in the note, click on **Save**. The new note will be saved in *BridgeTrak* with an Activity Type of "Customer Note", as shown in the example below:



When the Customer clicks on the Attachments tab in the View/Modify Issue window, *BridgeAccess* will display a window like the one shown below:

The window displays all files that have been attached to the Issue. To attach a new file, click on **Browse**. *BridgeAccess* will display a standard Windows directory. Click on the file that you want to attach and then click on **Open**. *BridgeAccess* will display the path and filename in the **Select File** field on the Attachments tab. When the file name is displayed, click on **Attach File**. The new file name will then be displayed in the File Name list. To view an attached file, click on it and then click on **View**.

5.1.2 Submitting Issues

To submit an Issue, click on **Issues | Submit New Issue**. *BridgeAccess* will display the Submit New Issue window, shown below:



The fields that have been defined in your Layout will be displayed. When you have completed entering information in the fields, click on **Save**. If any required fields have been left empty, *BridgeAccess* will display a message like the one shown below:

If you want to add an Activity note to the Issue, click on **Add Note**. *BridgeAccess* will display the Add Note window, shown below:

If you want to attach a file to the Issue, click on the Attachments tab. *BridgeAccess* will display the window, shown below:



Click on **Browse** and *BridgeAccess* will display the standard windows directory, like the one shown below:



Click on the file that you want to attach and then click on **Open**. *BridgeAccess* will display the path and file name in the **Select File** field. When the file name is displayed, click on **Attach File**. The file name will be displayed on the Attachments tab, as shown in the example below:

6 The Knowledge Base

In addition to submitting and viewing Issues, *BridgeAccess* also gives your Customers access to your *BridgeTrak* Knowledge Base.

To search the Knowledge Base, click on **Tools | Knowledge Base**. *BridgeAccess* will display the Knowledge Base Search window, shown below:


Kemma Software
Demo Site
Issues
Tools
Help
Logout
Welcome, Karunanidhi Kumar. Today is Sunday Feb 26, 2006
Knowledge Base Search
Article ID
Category
Sub Category
Product Name
Search Knowledge Base for word(s) or phrase
Search For
All of the words entered
Search In
Full Text
Search
Reset
Article ID
Title
K107 What to do when User is unable to add data.
K108 What to do when receiving error messages when deleting attachment files.
K110 Issues When Sending Email to External Customers
K111 Errors When Running Reports
K112 How X-Track Financial Totals are Calculated
K113 How to Use the Budget Report Writer
K114 How to Set Up Employee Records
K115 How to Import Data
K116 Installing User Options Module
K117 Automatically Generating Record Numbers
Page 1 of 2.

Using the Knowledge Base Search window, your Customers can find:

- All Articles belonging to a particular Category.
- All Articles belonging to a particular Sub Category.
- All Articles pertaining to a particular Product.
- A specific Article identified by the Article ID.

Customers can also search for Articles containing a specific word, phrase, or Keyword.

Enter the search criteria in the fields in the Knowledge Base Search window, using the table below as a guideline.

Field	Description
Category	If you want to search for all Articles belonging to a particular Category, select the Category from the drop-down menu.
Sub Category	If you want to search for all Articles belonging to a particular Sub Category, select the Sub Category from the drop-down menu. The Sub Category drop-down menu will not be populated until a Category is selected in the field above. Then, only the

Field	Description
	Sub Categories for the selected Category will be available for selection.
Product Name	If you want to search for all Articles pertaining to a particular Product, select the Product Name from the drop-down menu.
Article ID	If you are searching for one Article in particular and you know its Article ID, enter the Article ID here.
Search Knowledge Base for word(s) or phrase	Enter the word(s) or phrase for which you want to search the Knowledge Base Articles. If there are more than one individual word you want to find, separate them with spaces or commas.
Search For	The Search For drop-down menu contains three options. The are: • **All of the words entered** – Finds only those Articles containing each and every word entered in the field above. • **Any of the words entered** – Finds Articles containing any word (one or more) entered in the field above. • **Exact Phrase** – Finds only those Articles that contain text that matches the phrase entered in the field above, word for word.
Search In	The Search In drop-down menu contains three options: They are: • **Full Text** – Searches the Articles' Titles and full text (including Description, Cause, Resolution, and URLs) for the word(s) or phrase entered in the field above. • **Title Only** – Searches only the Articles' Titles for the word(s) or phrase entered in the field above. • **Keywords Only** – Searches only the Articles' Keywords for the word(s) or phrase entered in the field above.

After entering your search criteria, click on **Search**. *BridgeAccess* will display the results of the search in a Knowledge Base Search Result window, like the one shown below:



Each Title in the list is a direct link to the Knowledge Base Article. The Knowledge Base Search Result window also provides a **Print** button that enables you to print out a list of Knowledge Base Article Titles.

When you click on the Article Title that you want to view, *BridgeAccess* will display a KB Search Article window, like the one shown below:

The top portion of the window displays the Article in scrollable format. The Article also shows the Article ID and the date on which it was last reviewed.

The bottom portion of the window shows the Titles of other Knowledge Base Articles that are related (if any). These Titles also provide a direct link to the Article.

If you would like to forward a KB article by email, you can click the Email button. The System Administrator must have first configured the email settings for this button to be enabled.

If there are additional files attached to the Article, the file names will be displayed when you click on the Attachments tab, as shown in the example below:



From here, you can open and view any Attachments associated with the Article. At the bottom of the Article is the following prompt:

Having your Customers respond to this prompt will help to keep the Knowledge Base as informative as possible.

Index

ActiveX Viewer....28
Add Fields Button....33
Add Fields Window....33
Add Note Button....40, 41
Adding Fields to a Layout....33
Approve Button....11
Article ID....45
Assigning Layouts to Companies....35
Attach File Button....40, 43
Cancel Button....12
Cannot Change Password Option....8
Category....44
Change Sequence Button....34
Change Sequence Window....34
Click Here if You Are a BridgeTrak Administrator Link....12
Company - Edit Window....35
Company Information....18
Company Website....18, 19
Contact Us Window....19
Custom Fields....33
Customer - Edit Window....7
Customer Login Window....5
Customer Logon Window....12
Customer Registration....8
Customer Registration and Validation....6
Customer Validation Window....10
Customize Layout Window....32
Default Value Column....32
Define Layouts Window....31
Defining Layouts....31, 32
Delete Column....32
Deny (Delete) Button....11
Deny (Retain) Button....12
Display Message Board Option....18, 19, 20
Editing Issues....39
Email Link....18
Field Name Column....32
Fields
  article id....45
  category....44
  company information....18
  company website....18, 19
  email link....18
  from email address....16
  from name....16
  issue no....36
  last login....8
  layout name....32
  login name....7
  logon name....13
  message subject....17
  password....13, 17
  product name....45
  search for....45
  search in....45
  search knowledge base for word(s) or phrase....45
  select file....40, 43
  signature block....17
  SMTP server....16
  SMTP user name....17
  status....36
  sub category....44
  timeline....36
  view....36
Forgot Logon Name and/or Password Link....6
Forgot Logon Name and/or Password Window....6
From Email Address....16
From Name....16
Grant Customer BridgeAccess Login Privilege Option....7
Header Logo....21
How Do I?
  add fields to layouts....33
  assign layouts to companies....35
  define layouts....31, 32
  edit issues....39
  log into BridgeAccess as a customer....5
  sequence fields....34
  submit issues....41
  validate customers to use BridgeAccess....7
  view issues....36
HTML Viewer....29
Issue No....36
Issues
  editing....39
  submitting....41
KB Search Article Window....46
Knowledge Base....44
  Hide from View....18
Knowledge Base Search Result Window....45
Knowledge Base Search Window....44
Last Login....8
Layout Name....32

Layouts
adding fields to 33
assigning to companies 35
defining 31, 32
sequencing fields in 34
Logging in as an Administrator 12
Logging Into BridgeAccess 5
as a customer 5
as an Administrator 12
Login Name Field 7
Logon
Forgot Logon Name 18
Logon Name 13
Logon Screen Logo 21
Logos
header 21
logon screen 21
report 29
Manage Message Board Window 19
Match/No Match Indicator 10
Message - Edit Window 19
Message Subject 17
More Search Criteria Window 37
Must Change Password Option 8
Open Customer Setup Window After Validation Option 11
Password 13, 17
Forgot Password 18
Passwords
cannot change 8
must change 8
Print All Issues Button 27
Print Selected Issues Button 27
Printable Column 32
Product Name 45
Read Only Column 32
Read the Message Link 18, 20
Register 18, 21
Register Link 5, 8
Registered Customers Window 9
Registration 6, 8
Registration Window 5, 8
Regular Fields 33
Report Logo 29
Report Viewer Types 28
ActiveX viewer 28
html viewer 29
Required Column 32
Search For 45
Search In 45
Search Knowledge Base for Word(s) or Phrase 45
Searchable Column 32
Select File 40, 43
Sequencing Fields 34
Set As Default Button 31
Signature Block 17
SMTP Server 16
SMTP User Name 17
Standard Layout 31
Status 36
Sub Category 44
Submit New Issue Window 41
Submitting Issues 41
System Options 14
System Options Window 14, 15
issue activity settings tab 24
logo settings tab 21
report settings tab 27
Timeline 36
User Setup Window 13
Validating Customers to Use BridgeAccess 7
Validation 6
View 36
View Company Issues Option 8, 11
View Department Issues Option 8, 11
View Issue Window 38
View Issues Window 36
View Location Issues Option 8, 11
View/Modify Issue Window 39
activities tab 39
attachments tab 40
issue tab 39
Viewer Type 28
Viewing Issues 36
Windows
add fields 33
change sequence 34
company - edit 35
contact us 19
customer - edit 7
customer login 5
customer logon 12
customer validation 10
customize layout 32
define layouts 31
forgot logon name and/or password 6
kb search article 46
knowledge base search 44
knowledge base search result 45
manage message board 19
message - edit 19
more search criteria 37
registered customers 9
registration 5, 8
submit new issue 41
system options 14, 15

user setup 13
view issue 38
view issues 36
view/modify issue window 39